


Win11 使用 yuntech-802.1x 無線網路認證操作說明：


1. 請先確認已經安裝 EAP-GTC 第三方模組
2. 開啟「網路和網際網路」選擇「撥號」，然後選擇「網路和共用中心」



3. 點選「設定新的連線或網路」



4. 點選「手動連線到無線網路」



5. 輸入網路相關資訊並勾選「自動啟動這個連線」 802.1x(x 是小寫)

手動連線到無線網路

輸入您要新增之無線網路的資訊

網路名稱(E): yuntech-802.1x

安全性類型(S): WPA2-Enterprise

加密類型(R): AES

安全性金鑰(C): ☐ 隱藏字元(H)

☒ 自動啟動這個連線(T)

☐ 即使網路未廣播，還是進行連線(O)

警告: 若選取此選項，您電腦的隱私權可能有風險。

下一步(N) 取消

6. 成功新增後，選擇 yuntech-802.1x 「變更連線設定」

手動連線到無線網路

已成功新增 yuntech-802.1x

→ 變更連線設定(H)
開啟 [連線] 內容讓我可以變更設定。

關閉

7. 在內容中，點選「安全性」，先調整如圖中之項目後，進入「設定」

The screenshot shows a Windows-style dialog box titled "yuntech-802.1x 無線網路內容" (yuntech-802.1x Wireless Network Content). It has a close button (X) in the top right corner. The dialog is divided into two tabs: "連線" (Connection) and "安全性" (Security). The "安全性" tab is selected and highlighted with a red box. Inside the "安全性" tab, there are several settings:

- "安全性類型(E):" (Security Type) is set to "WPA2-Enterprise" via a dropdown menu.
- "加密類型(N):" (Encryption Type) is set to "AES" via a dropdown menu.
- "選擇網路驗證方法(O):" (Select Network Authentication Method) is set to "Microsoft: Protected EAP (PEAP)" via a dropdown menu. To the right of this dropdown is a button labeled "設定(S)" (Settings), which is highlighted with a red box.
- Below the dropdown is a checked checkbox labeled "每次登入時都記住我在此連線的認證(R)" (Remember my credentials for this connection every time I log in).
- At the bottom left of the tab area is a button labeled "進階設定(D)" (Advanced Settings).

At the bottom of the dialog box, there are two buttons: "確定" (OK) and "取消" (Cancel).

8.

8-1 取消「確認伺服器憑證」的勾選

8-2 選擇驗證方法「EAP-MSCHAPV2」

8-3 勾選「啟用快速重新連線」

受保護的 EAP 內容

連線時:

☐ 透過驗證憑證來確認伺服器身分識別(V)

☐ 連線到這些伺服器(例如:svr1;svr2;*\svr3\com)(O):

受信任的根憑證授權單位(R):

- ☐ AAA Certificate Services
- ☐ Bypass Class 2 Root CA
- ☐ Certum CA
- ☐ Certum Trusted Network CA
- ☐ Class 3 Public Primary Certification Authority
- ☐ COMODO RSA Certification Authority
- ☐ DigiCert Assured ID Root CA
- ☐ DigiCert Global Root CA
- ☐ DigiCert Global Root G2

連線前的通知(T):

如果無法驗證伺服器的身分識別則告知使用者

選擇驗證方法(S):

Secured password (EAP-MSCHAP v2)

設定(C)...

☒ 啟用快速重新連線(F)

☐ 如果伺服器未顯示加密繫結的 TLV 就中斷連線(D)

☐ 啟用識別隱私權(I)

確定 取消

9. 確定後，回步驟 7，選擇「進階設定」

yuntech-802.1x 無線網路內容

連線 安全性

安全性類型(E): WPA2-Enterprise

加密類型(N): AES

選擇網路驗證方法(O):

Microsoft: Protected EAP (PEAP) 設定(S)

☒ 每次登入時都記住我在此連線的認證(R)

進階設定(D)

確定 取消

10. 於「802.1X 設定」項目，勾選「指定驗證模式」，選擇「使用者驗證」

進階設定

802.1X 設定 802.11 設定

☒ 指定驗證模式(P):

使用者驗證

儲存認證(C)

☐ 刪除所有使用者的認證(D)

☐ 對此網路啟用單一登入(S)

☒ 在使用者登入前立即執行(E)

☐ 在使用者登入後立即執行(F)

最大延遲(秒)(M): 10

☒ 單一登入期間允許顯示其他對話方塊(L)

☐ 此網路使用不同的虛擬 LAN 來驗證電腦和使用者(V)

確定 取消


11.完成建立無線網路的 profile。日後，若想要更動個別 profile 的設定，您可以直接在選擇無線網路的 SSID 上，按下滑鼠右鍵，選「檢視連線內容」，即可進入設定的頁面。

12.輸入帳號密碼

帳號:(學校單一入口帳號，若漫遊使用者請加@yuntech.edu.tw)、

密碼: (學校單一入口密碼)

Login domain：請留空白



13.完成連線